



# WebEvalClient Utility

**For ImageGear Products  
For All Platforms**





# Table of Contents

---

<b>WebEvalClient Utility</b> .....	<b>1</b>
How to Run WebEvalClient Utility .....	1
How to Use WebEvalClient Utility .....	1
Environment Parameter Screen .....	3
License Key Screen .....	4
How to Use Your License Key .....	5
License Expired Screen .....	6
Status Message Screen .....	8



# WebEvalClient Utility

---

**WebEvalClient** utility is a Web application, allowing you to manage your AccuSoft products evaluation licenses in a very easy and flexible way. Using this utility you can:

- generate a new evaluation license key
- check your existing evaluation license key
- submit a request for evaluation period extension

---

**NOTE:** Using **WebEvalClient** you can manage evaluation licenses for any platforms. However, for Microsoft Windows platforms we recommend you using **AccuSoft License Manager** utility, because it obtains the hardware parameters automatically.

---

## How to Run WebEvalClient Utility

To run **WebEvalClient** utility please type URL:

<https://licensing.accusoft.com/v1/webevalclient/product.aspx>

in the address combo box of Internet Explorer and press **Enter**.

## How to Use WebEvalClient Utility

This is the **Entry** screen of the **WebEvalClient** utility:

## ImageGear Licensing

### Leading the industry in customer support

Companies rely on AccuSoft for quality support and follow-through.

Welcome to the ImageGear Evaluation Licensing site.

Welcome to the ImageGear evaluation page! Please select the product platform and enter the e-mail and password you have obtained when requesting evaluation version of the product. If you have not registered yet please [register now](#).

Email:	<input type="text"/>
Password:	<input type="password"/>
Platform:	<input checked="" type="radio"/> Linux <input type="radio"/> SunSolaris <input type="radio"/> HP-UX <input type="radio"/> AIX <input type="radio"/> Mac <input type="radio"/> Java <input type="radio"/> Windows <input type="radio"/> .NET <input type="radio"/> .NET 64-bit <input type="radio"/> Windows 64-bit <input type="radio"/> Unix 64-bit <input type="button" value="Login"/>

Please do the following:

1. Select the product platform for which you are going to manage an evaluation license.
2. Enter **e-mail** and **password** you have obtained when requested an evaluation version of the product.

---

---

**NOTE:** If you still have not registered yet, you can do so by clicking on the **register now** link.

---

---

3. Press the **Login** button to proceed to the next screen.

Depending on the platform type you have selected and your product evaluation license status you should get one of the following three screens:

- If you have selected any platform, except **Java**, and if you have not requested an evaluation license for this platform earlier, you get the [Environment Parameter Screen](#).
- If you have selected **Java** platform, or if you have already requested an evaluation license and it has not expired yet, you get the [License Key Screen](#).
- If you have already requested an evaluation license and it has expired, you get the [License Expired Screen](#).

## Environment Parameter Screen

If you use ImageGear Unix, please run the **EnvParamsUtility** to obtain the hardware ID of your system. This utility is located in the following directory of your ImageGear Unix installation:

**AccuSoft/ImageGear/<Version>/Utils/<Unix OS>/**

Then enter this ID exactly as reported by the utility into the form and click the **Generate** button to obtain your license key:

### ImageGear Licensing

Leading the industry in customer support

Companies rely on AccuSoft for quality support and follow-through.

Please run AccuSoft's hardware identification utility for Linux. This will display the hardware ID of your machine. Enter this ID into the form and click the button to obtain your license key.

[Documentation](#)

## License Key Screen

This screen shows your license key and lists the terms of the license usage.

### ImageGear Licensing

Leading the industry in customer support

Companies rely on AccuSoft for quality support and follow-through.

Your evaluation license key is provided below. It entitles you to use all the features of ImageGear for the Java platform for a limited period of time - 15 days. It will expire on 7/6/2006 12:00:00 AM US Eastern Time.

```
0.9.0HrcYzNQF3Em6mDQ6Rz3D3rzY1EcPmEm6ODL67DRF79
QPTrmYQt3r8MQWT9IDLxQDRNJE3x1DmPvZTxmY1Zcr36LPO
6cD3t7v8N367D1r7YT6OYT04
```

[Documentation](#)

If you want to request an evaluation license for another platform, click the **Logout** button to return to the **Entry** screen.

## How to Use Your License Key

When the license key is obtained, please do the following (depending on your ImageGear platform):

- **For ImageGear Unix:**

Insert your license key in the "accusoft.AccuSoft 1-101-16.imagegear", which is included to the installation and is located in the following directory:

## AccuSoft/ImageGear/<Version>/Unix/

When it's done the variable `IMAGE_GEAR_LICENSE_DIR` has to be defined and should contain the path to the license file, for example:

```
IMAGE_GEAR_LICENSE_DIR=$HOME/AccuSoft/ImageGear/Professional  
Edition/Unix/
```

If the `IMAGE_GEAR_LICENSE_DIR` variable is not defined, ImageGear will look for the license file in `/usr/lib/` directory.

For more details please refer to **INSTALL.TXT** file located in the following directory of your ImageGear installation:

## AccuSoft/ImageGear/<Version>/Unix/

### ■ For ImageGear Java

Insert your license key in the **License.java** file as follows:


```
package accusoft.Samples.Shared;  
  
public class License extends Object  
{  
    public final static String Key = "<your license key>";  
}
```

The **License.java** file is located in the following directory:

**/AccuSoft/ImageGear/<Version>/Java/Samples/accusoft/Samples/Shared/**

## *License Expired Screen*

This screen shows you that your evaluation license has already expired:



You can choose the one of the two following ways:

- If you want to submit request for a new key, click the **Submit Extension Request** button.
- If you want to request an evaluation license for another platform, click the **Logout** button to return to the **Entry** screen.

## *Status Message Screen*

This screen reports the status of your Licensing Center session. If this screen reports a problem, please forward problem description to AccuSoft Customer Support.

## A

AccuSoft License Manager utility . . . . . 1

## E

e-mail and password . . . . . 2

Entry screen . . . . . 1

Environment Parameter Screen . . . . . 3

EnvParamsUtility

    Obtaining hardware ID (for Unix) 3

## I

Inserting license key

    For ImageGear Java 6

    For ImageGear Unix 5

## J

Java platform licensing . . . . . 3

## L

License Expired Screen . . . . . 3, 6

License Key Screen . . . . . 3, 4

## P

product platform . . . . . 2

## S

Status Message Screen . . . . . 8

## W

WebEvalClient URL . . . . . 1

WebEvalClient utility . . . . . 1

Windows platform licensing . . . . . 1